

DuPont model of Profit Analysis

**Agribusiness Finance
LESE 306 Fall 2009**

DuPont Formula


- ✓ ROA can be broken down into profit margin and asset turnover.
- ✓ Gain an insight into planning for profit improvement.
- ✓ Need to improve the profit margin.
- ✓ Need to improve asset turnover.
- ✓ Need to improve both!!

Improving Profit Margin

- ✓ Reducing expenses:
 - Using less costly materials.
 - Automation to improve productivity.
 - Review fixed costs (advertising, R&D, management development programs, etc.).
- ✓ Raising prices:
 - Requires pricing power.
 - Also requires brand loyalty.
 - Easier for firms with unique high quality goods.

Improve Asset Turnover

- ✓ Increase sales while holding investment in assets relatively constant:
 - Dispose of obsolete and redundant assets.
 - Speed up collections of receivables.
 - Evaluate credit terms and policies.
 - Identify unused fixed assets.
- ✓ Use idle cash to repay outstanding debts or invest in profit producing activities.



Problem #2: Fall 2009

Cash	\$10,000
Cash receipts from sales	\$73,000
Cash operating expenses	\$51,200
Time and savings deposits	\$11,000
Other current assets	\$22,000
Machinery and equipment	\$76,500
Buildings	\$14,000
Land	\$99,500
Hired labor expenses	\$7,000
Allowance for income taxes	\$7,213
Accounts payable	\$1,200
Current payment on term loan	\$7,500
Remaining balance on term loan	\$29,500
Other long term liabilities	\$1,200
Depreciation	\$7,400
Interest payments on term loans	\$2,500
Principal payments on term loans	\$5,000

Year End Balance sheet

Cash	\$10,000	Current payment on term loan	\$7,500
Time and savings deposits	\$11,000	Accounts payable	\$1,200
Other current assets	\$22,000	Allowance for income taxes	\$7,213
Total current assets	<u>\$43,000</u>	Total current liabilities	\$15,913
Machinery and equipment	\$76,500	Remaining balance on term loan	\$29,500
Buildings	\$14,000	Other long term liabilities	\$1,200
Land	\$99,500	Total noncurrent liabilities	\$30,700
Total noncurrent assets	<u>\$190,000</u>	Total liabilities	<u>\$46,613</u>
Total assets	<u>\$233,000</u>	Equity or net worth	<u>\$186,387</u>
		Total claims on business	\$233,000

Liquidity ratios:

Current ratio	2.70
Working capital	\$27,087
Acid test ratio	1.32
Cash ratio	0.63

Solvency ratios:

Debt ratio	0.20
Net worth ratio	0.80
Asset ratio	5.00
Leverage ratio	0.25

Debt repayment capacity ratios: 1/

Term debt and capital lease coverage ratio	1.94
Times interest earned ratio	2.87
Debt burden ratio	9.95

Earnings before interest and taxes	\$14,400
Allowance for income taxes	\$7,213
EBIT - taxes	<u>\$7,187</u>

Definitions of coverage ratio:

1. After-tax coverage ratio	0.96
2. After-tax cash coverage ratio	1.94

Annual Income Statement

Cash receipts from sales	<u>\$73,000</u>
Total revenue	\$73,000
Cash operating expenses	\$51,200
Interest expenses	\$2,500
Depreciation	\$7,400
Total expenses	<u>\$61,100</u>
Net income before taxes	\$11,900
Allowance for income taxes	\$7,213
Net income	<u>\$4,687</u>


Profitability ratios:

Rate of return on assets	<u>2.01%</u>
Rate of return on equity	<u>2.51%</u>
Net profit margin	<u>6.42%</u>

Efficiency ratios:

Variable expense ratio	70.14%
Interest expense ratio	3.42%
Depreciation expense ratio	10.14%
Total asset turnover ratio	31.33%
Fixed asset turnover ratio	38.42%

1/ See the formulas on page 15 of the booklet for further discussion of these ratios.



DuPont Formula

The use of borrowed funds can magnify returns to equity. To see this, consider the following definitions using problem 2 values:

$$\begin{aligned}\text{ROE} &= \text{Net income} / \text{Equity} \\ &= \$4,687 / \$186,387 = .0251\end{aligned}$$

DuPont Formula

The use of borrowed funds can magnify returns to equity. To see this, consider the following definitions using problem 2 values:

$$\begin{aligned}\text{ROE} &= \text{Net income} / \text{Equity} \\ &= \$4,687 / \$186,387 = .0251\end{aligned}$$

or

$$\begin{aligned}\text{ROE} &= (\text{Net income} / \text{Total assets}) \times (\text{Total assets} / \text{equity}) \\ &= (\$4,687 / \$233,000) \times (\$233,000 / \$186,387) = .0251\end{aligned}$$

DuPont Formula

The use of borrowed funds can magnify returns to equity. To see this, consider the following definitions using problem 2 values:

$$\begin{aligned}\text{ROE} &= \text{Net income} / \text{Equity} \\ &= \$4,687 / \$186,387 = .0251\end{aligned}$$

or

$$\begin{aligned}\text{ROE} &= (\text{Net income} / \text{Total assets}) \times (\text{Total assets} / \text{equity}) \\ &= (\$4,687 / \$233,000) \times (\$233,000 / \$186,387) = .0251\end{aligned}$$

or

$$\begin{aligned}\text{ROE} &= \text{ROA} \times \text{Equity multiplier} \\ &= .0201 \times 1.25 = .0251\end{aligned}$$

where:

$$\text{Equity multiplier} = \text{Total assets} / \text{Equity} = \$233,000 / \$186,387 = 1.25$$

or

$$\text{Equity multiplier} = 1 / (1 - \text{Debt ratio}) = 1 / (1 - .20) = 1 / .80 = 1.25$$



DuPont Formula

Because it links several critical ratios, the DuPont formula allows you to examine how a firm generates its ROE.

NI = Net income = \$4,687

NPM = Net profit margin = .0642

TA = Total assets = \$233,000

EM = equity multiplier = $1 / (1 - \text{Debt ratio}) = 1.25$

TAT = Total asset turnover ratio = $\text{Sales} / \text{Total assets} = .3133$

ROE = $\text{NPM} \times \text{TAT} \times \text{EM} = .0642 \times .3133 \times 1.25 = .0251$

DuPont Formula

Because it links several critical ratios, the DuPont formula allows you to examine how a firm generates its ROE.

NI = Net income = \$4,687

NPM = Net profit margin = .0642

TA = Total assets = \$233,000

EM = equity multiplier = $1 / (1 - \text{Debt ratio}) = 1.25$

TAT = Total asset turnover ratio = $\text{Sales} / \text{Total assets} = .3133$

ROE = $\text{NPM} \times \text{TAT} \times \text{EM} = .0642 \times .3133 \times 1.25 = .0251$

or

ROE = $(\text{NI} / \text{TA}) \times \text{EM} = (\$4,687 / \$233,000) \times 1.25 = .0251$

Analyzing DuPont Formula

1. A high net profit margin or NPM signals *strong operating management*.
2. A high total asset turnover ratio or TAT signals *strong asset management*.
3. A high equity multiplier or EM signals *strong capital management* in the presence of low and stable cost of debt capital.

Examining an Economic Growth Model